LANDesk® Management Suite 8.8 Installation Guide for a Rollup Core Server

Introduction

This document is intended to assist LANDesk® Management Suite 8.8 (Management Suite) customers with installing a Rollup Core Server. It also contains some troubleshooting tips for the Rollup Core Server.

Scope

This document covers the steps necessary to install a Rollup Core Server and to Rollup a Core Server's database.

Assumptions

The reader should be familiar with Management Suite. The Management Suite Core Server should already be installed and operational.

Installing the Rollup Core Server

The following sections describe the procedure for installing the Rollup Core Server.

Part I: Setting up the database for the Rollup Core Server.

How to create the database for the Rollup Core Server:

- Create the database for the Rollup Core Server using the same procedure used for the Core Server's database.
- Create the Database Links

Complete installation instructions for Microsoft SQL Server 2000/2005 http://community.landesk.com/support/docs/DOC-1097

Complete installation instructions for Oracle http://community.landesk.com/support/docs/DOC-1663


Part II: Installing the Rollup Software on the Rollup Core Server

How to install the Rollup Core Server:


- Log in to the Windows 2000 or 2003 server that will be the Rollup Core Server with an Administrator account.
- Run the LDMS 8.8 software.exe used to install the ManagementSuite.




Select the autorun.exe and the below window will open and choose Rollup Core




4. Click install now.




5. Select your language




6. Click Next




7. Accept the license and click next.




8. Select your install directory and click next



9. Choose if you wish to add a web console to your rollup core.




10. Enter the database information created in the database setup from Part I, Step 1.




11. Enter your Organization Name and Certificate Name.

i₿LANDesk(R) Software setup		×
Security certificate		LANDesk*
Every core server must have a security certificate to guarantee its identity. Devices communicate with a core server only if they have a certificate for it.		
If you are replacing an existing core	e server and want your new serve e same Organization and Certifica	Setup will create the certificate for you. ver to use the same certificate, copy it from the old server sate name here will not create the same certificate, and
<u>O</u> rganization:	Org	
Certificate name:	Cert	
		< Back Next > Cancel

12. Click Install




LANDesk Install




Note: After you reboot you will want to patch your Rollup Core to the same level as your Core. For example if you are on 8.8 SP1 you will need to download the 8.8 SP1 Rollup Core patch and execute on the Rollup Core.

14. Open the Database Rollup Utility found in the Start Menu under Progam Files > Landesk. Drop down to your roll up core and press add. You will then put in your core server name and the link name from Part I, Step 2.



16. Click on the attributes button and choose which items you would like.





17. Highlight the coreserver name and click on rollup.

